# Parallel and Distributed Data Management Database System Architectures


Nikolaus Augsten

nikolaus.augsten@plus.ac.at
Department of Computer Science
University of Salzburg



### Sommersemester 2025

Version 9. April 2025



# Outline

### 1 Centralized and Client-Server Systems

2 Server System Architecture


### 3 Parallel Systems

- Performance Measures
- Interconnection Networks
- Parallel Database System Architecture

### Distributed Systems

# Centralized Database Systems

- Run on a single, centralized computer system that does not interact with other computer systems.
- A centralized computer system may run single-user or multi-user systems.



# Single-User and Multi-User Systems

• Single-user system (e.g., smartphone or personal computer): single user, usually has only one CPU (with multiple cores) and one or two disks; the OS may support only one user.


• Multi-user system: more disks, more memory, multiple CPUs, and a multi-user OS. Serve a large number of users who are connected to the system remotely. Often called server systems.

# Embedded Databases

### • Databases on single-user systems may come with limited functionality:

- simple concurrency control schemes
- basic (e.g., copy before update) or no recovery mechanisms
- provide API instead of declarative interface like SQL


• Such systems are called embedded databases and are typically linked to a single application.




#### Centralized and Client-Server Systems

# Client-Server Systems/2

- Database functionality can be divided into:
  - back-end: manages access structures, query evaluation and optimization, concurrency control and recovery
  - front-end: consists of tools such as forms, report-writers, and graphical user interface facilities
- The interface between the front-end and the back-end is through SQL or through an application program interface.






Server System Architecture

# Server System Architecture

- Server systems can be broadly categorized into two kinds:
  - transaction servers which are widely used in relational database systems
  - data servers traditionally used in object-oriented database systems



# Transaction Server Process Structure/1

• A typical transaction server consists of multiple processes accessing data in shared memory.

#### • Server processes


- receive user queries (transactions), execute them, and send results back
- processes may be multithreaded, allowing a single process to execute several user queries concurrently
- typically multiple multithreaded server processes run concurrently (e.g., one multithreaded process per user session)


#### • Lock manager process

• grants and releases locks, detects deadlocks

#### • Database writer process

output modified buffer blocks to disks continually





#### Server System Architecture


### Transaction Server Process Structure/4

- All database processes can access shared data:
  - buffer pool
  - lock table
  - log buffer
  - cached query plans (reuse plan if same query is submitted again)
- To avoid two processes accessing the same data structure at the same time, databases systems implement mutual exclusion using either
  - operating system semaphores (wait and signal operations)
  - atomic instructions (test-and-set or compare-and-swap)
- To avoid overhead of message passing (sending requests to lock manager) for lock request/grant, database processes may operate directly on the lock table
- Lock manager process still used for deadlock detection

#### Server System Architecture

### Data Servers

- Originally developed for object-oriented databases:
  - create, retrieve, and update persistent objects
  - persistent objects are accessed like main memory objects in programming languages
- All computations performed on client:
  - server ships required data items to client
  - client performs compute intensive tasks on data items
  - updated or new data items are shipped from client to server
- Server only needs to store and fetch data.
- Data servers are typically used when
  - the client performs extensive computations, e.g., a CAD system fetches a computer chip model and runs simulations
  - client and server are connected via high-speed network



- Client and server communicate via network:
  - network latency (also network round-trip time) is the time to send a message over a network and get response back
  - much slower than local memory references, e.g., milliseconds vs. 100 nanoseconds even in LAN (local are network)
- Optimization strategies to reduce the effect of network latency:
  - prefetching: send a data item before it is requested
  - data caching: client caches data received from server for future use
  - lock caching: client keeps the lock also after accessing the data
  - adaptive lock granularity: use coarse- and fine-grained locks to balance number of lock requests and lock contention

# Caching at Clients/2

#### • Prefetching

- network latency is per request: similar for large and small messages
- sending one item at a time has a large overhead
- prefetching sends also data items that are not requested, but are likely to be used in the near future

### • Data Caching

- data can be cached at client even in between transactions
- but check that data is up-to-date before it is used (cache coherence)
- check can be done when requesting lock on data item

# Caching at Clients/3


#### • Lock caching

- requesting and granting a lock requires a network round trip
- locks can be retained by client system even in between transactions
- transactions can acquire cached locks locally, without contacting server
- server calls back locks from clients when it receives conflicting lock request; client returns lock once no local transaction is using it
- works well when data is partitioned among clients, i.e., two different clients rarely request lock on the same data item

# Caching at Clients/4

#### • Adaptive lock granularity

- multi-granularity locking: locks not only on individual data items (fine granularity), but also on pages, tables, etc. (coarse granularity)
- avoid large number of locks, e.g., get a single page lock instead of multiple item locks on that page
- coarse-granularity locks decrease number of locks but increase lock contention (i.e., transactions have to wait for a lock)
- lock de-escalation adaptively decreases the lock granularity when there is lock contention:
  - 1. server sends de-escalation request to client
  - 2. client requests finer-granularity locks
  - 3. when finer-granularity locks are granted, coarse-granularity lock is released



# Parallel Systems

- Parallel database systems consist of multiple processors and multiple disks connected by a fast interconnection network.
- A coarse-grain parallel machine consists of a small number of powerful processors
- A massively parallel or fine grain parallel machine utilizes thousands of smaller processors.
- Two main performance measures:
  - throughput the number of tasks that can be completed in a given time interval
  - response time the amount of time it takes to complete a single task from the time it is submitted

# Speed-Up and Scale-Up


- Speedup: a fixed-sized problem executing on a small system is given to a system which is *N*-times larger.
  - Measured by:


 $speedup = \frac{small \ system \ elapsed \ time}{large \ system \ elapsed \ time}$ 

- Speedup is linear if equation equals *N*.
- Scaleup: increase the size of both the problem and the system
  - N-times larger system used to perform N-times larger job
  - Measured by:

 $scaleup = rac{small \ system \ small \ problem \ elapsed \ time}{big \ system \ big \ problem \ elapsed \ time}$ 

• Scaleup is linear if equation equals 1.





# Batch and Transaction Scaleup

#### • Batch scaleup: single large job.

- typical for decision support queries and scientific simulations
- use an N-times larger computer on N-times larger problem

#### • Transaction scaleup: numerous small queries.

- submitted by independent users to a shared database
- typical for transaction processing and timesharing systems
- N-times as many users submitting requests (hence, N-times as many requests) to an N-times larger database on an N-times larger computer
- well-suited to parallel execution

# Factors Limiting Speedup and Scaleup


Speedup and scaleup are often sublinear due to:

- Startup costs: Cost of starting up multiple processes may dominate computation time if the degree of parallelism is high.
- Interference: Processes accessing shared resources (e.g., system bus, disks, or locks) compete with each other, thus spending time waiting on other processes rather than performing useful work.
- Skew: Increasing the degree of parallelism increases the variance in service times of tasks executing in parallel. Overall execution time determined by slowest of tasks executing in parallel.

# Interconnection Network Architectures

- Bus: System components send data on and receive data from a single communication bus:
  - does not scale well with increasing parallelism.
- Mesh: Components are arranged as nodes in a grid, and each component is connected to all adjacent components:
  - number communication links grow with growing number of components, and so scales better
  - the number of hops to send message to a node is proportional to  $\sqrt{n}$
- Hypercube: Components are numbered in binary; components are connected to one another if their binary representations differ in exactly one bit.
  - *n* components are connected to log(n) other components
  - can reach each other via at most log(n) links
  - reduces communication delays


28 / 50



# Network Types

 Local-area networks (LANs) — composed of processors that are distributed over small geographical areas, such as a single building or a few adjacent buildings.

• Wide-area networks (WANs) — composed of processors distributed over a large geographical area.



# Local-Area Network/2

- Link technology: twisted pair, coaxial cable, fiber optics, wireless connection
- Ethernet: Specification for computer networks
  - Software (e.g., protocols)
  - Hardware (e.g., cables, network cards, switches)
- Transfer rates
  - Fast Ethernet: 1, 10, 100 Mb/s (1 Mb/s =  $10^6$  bits / second )
  - Gigabit Ethernet: 1 Gb/s
  - Widely used: 10 Gb/s, highest transfer rate: 400 Gb/s
  - Higher transfer rates (1 Tb/s) require new technologies

#### • Distances:

- usually single building or neighboring buildings
- up to 70km with fiber optics

### Wide-Area Network

- Fast wide-area links (fiber optics, satellite channel): hundreds of gigabits
- Last link typically slower (e.g., cable modem, wireless connection): some megabits
- Latency higher than in LAN
  - speed of light delay
  - queuing delay at routers
- WANs with continuous connection (e.g., the Internet) are needed for implementing distributed database systems.


## Example: Network Latency

- What are the number of routers and the network latency for
  - localhost (i.e., network connection to the local machine)
  - in the LAN (e.g., ssh.cosy.sbg.ac.at)
  - in the WAN (e.g., www.tum.de, unsw.edu.au)
- Use ping to measure latency and traceroute to learn how the network packets are routed


# Parallel Database Architectures

- Shared memory —processors share a common memory
- Shared disk processors share a common disk
- Shared nothing processors share neither a common memory nor common disk
- Hierarchical hybrid of the above architectures


# Parallel Database Architectures




shared memory



shared nothing



shared disk



hierarchical

#### Shared Memory

- Processors have access to a common memory via bus or interprocessor communication network.
- Extremely efficient communication between processors  $(< 1\mu s)$  data in shared memory can be accessed by any processor.
- Memory bus becomes a bottleneck since only a single processor at a time can use the bus.
- NUMA (non-uniform memory access):
  - each processor has locally connected memory
  - processors can access memory of other processors through a high-speed interprocessor communication network
  - locally connected memory is faster
- Does not scalable beyond a few hundred cores:
  - limited by bus speed and number processors that can be interconnected
  - widely used for lower degrees of parallelism


### Shared Disk/1

- All processors can directly access all disks via an interconnection network, but the processors have private memories.
  - The memory bus is not a bottleneck
  - Architecture provides a degree of fault-tolerance if a processor fails, the other processors can take over its tasks since the database is resident on disks that are accessible from all processors.
- Examples: IBM Sysplex and DEC clusters (now part of Compaq) running Rdb (now Oracle Rdb) were early commercial users
- Downside: bottleneck now occurs at interconnection to the disk subsystem.
- Shared-disk systems scale to a larger number of processors, but communication between processors is slower (some *ms*).

## Shared Disk/2

• File server / NAS (Network Attached Storage)

- disks connected via RAID controller
- mounted as directory in file system
  - Samba
  - NFS Network File System
- SAN Storage Array Network
  - block level access
  - appears to be locally attached block device
  - shared disk file system runs on top of SAN
    - IBM GPFS (General Parallel FS)
    - Oracle Cluster FS
    - Lustre (mainly super computing/Linux)



#### Shared Nothing


- Node consists of a processor, memory, and one or more disks.
- Nodes function as servers for the data on the disks they own.
- Communication between processors through interconnection network.
- Examples: Teradata, Tandem, Oracle-n CUBE
- Minimize interference of resource sharing: data accessed from local disks (and local memory accesses) do not pass through interconnection network
- Can be scaled up to thousands of processors without interference.
- Main drawbacks:
  - cost of communication
  - cost of non-local disk access
  - sending data involves software interaction at both ends

# Hierarchical


- Combines characteristics of shared-memory, shared-disk, and shared-nothing architectures.
- Top level is a shared-nothing architecture nodes connected by an interconnection network, and do not share disks or memory with each other
- Each node of the system could be a shared-memory system with a few processors.
- Alternatively, each node could be a shared-disk system, and each of the systems sharing a set of disks could be a shared-memory system.
- Reduce the complexity of programming such systems by distributed virtual-memory architectures

# Disaggregated Memory Architecture

- compute nodes: strong CPUs, small memory (cache)
- memory nodes: large memory, wimpy CPU
- fast network: low latency and high bandwidth



43 / 50




# Distributed Systems

• Data spread over multiple machines (called sites or nodes).

Distributed Systems

• Network interconnects the machines.




### **Distributed** Databases

#### • Homogeneous distributed databases

- same software/schema on all sites
- data may be partitioned among sites
- goal: provide a view of a single database, hiding details of distribution

#### • Heterogeneous distributed databases

- different software/schema on different sites
- goal: integrate existing databases to provide useful functionality



47 / 50

#### Distributed Systems

#### Trade-offs in Distributed Systems

- Sharing data: users can access data residing at some other sites (heterogeneous distributed databases)
- Autonomy: each site retains a degree of control over data stored locally (heterogeneous distributed databases)
- Higher system availability through redundancy: data can be replicated at remote sites, and system can function even if a site fails.
- Disadvantage: proper coordination among sites adds complexity.
  - software development cost
  - greater potential for bugs
  - increased processing overhead

48 / 50

## Implementation Issues for Distributed Databases

- Atomicity for transactions that update data at multiple sites
- The two-phase commit protocol (2PC) is used to ensure atomicity
  - Basic idea: each site executes transaction until just before commit, and then leaves final decision to a coordinator
  - Each site must follow decision of coordinator, even if there is a failure while waiting for coordinators decision
- 2PC is not always appropriate: other transaction models based on persistent messaging and workflows are also used
- Distributed concurrency control (and deadlock detection) required
- Data items may be replicated to improve data availability

# Conclusion

• Homogeneous vs. heterogeneous distributed database systems.

• Distributed database different from a shared nothing parallel systems.

- Geographical separation of sites comes with opportunities and challenges:
  - higher availability through geographically distributed redundancy
  - new implementation challenges